

DEEP SCRUB & RECOAT

Tools Needed

- Wet Floor Sign
- Clean Cotton Mop (application step)
- Clean Rayon Mop (rinse step)
- 2 Mop Buckets and Wringers
- Rotary Scrubber and Pads
- Doodlebug
- Wet Vacuum
- Squeegee

Product Needed (2 Options)

P&G Pro Line®
Finished Floor Cleaner


Mr. Clean®
Finished Floor Cleaner



FREQUENCY OF CLEANING: Monthly or as needed when preventative maintenance (burnish, spray buff, restore) does not leave floor to desired appearance. Floors will show slight traffic lane wear, scratches, soiling etc.

PREPARATION: Collect all tools, equipment and products required. Ensure all equipment is operational. Review MSDS, product labels and caution statements. Choose appropriate safety equipment.

SPECIAL DIRECTIONS FOR THIS TASK: Empty mop bucket when finished. Leave wet floor sign in place until floor is completely dry. Clean and return equipment to storage area when finished.




STEP 1

- Remove grit and loose soil by following the Dust Mop Procedure.



STEP 2

- Put out wet floor sign in area to be mopped.



STEP 3

- Fill mop bucket with 4 gallons of water.

For P&G Pro Line Finished Floor Cleaner:


- Add 8 ounces of floor cleaner to 4 gallons of water (2 ounces per gallon of water)

For Mr. Clean Finished Floor Cleaner:

- Add 16 ounces of floor cleaner to 4 gallons of water (4 ounces per gallon of water)

- Fill second mop bucket with clear water.

NOTE: Clear water mop bucket will be used for rinsing.




STEP 4

- Submerge cotton mop in solution.
- Move mop up and down until mop is thoroughly wet.




STEP 5

- Apply cleaning solution liberally to 10 ft. by 20 ft. area, making sure surface remains wet.




STEP 6

- Let stand for 5 minutes, making sure solution does not dry.




STEP 7

- Machine agitate with appropriate pad. Avoid splashing walls.
- Agitate all areas thoroughly.
- Scrub edges and corner with doodle bug.
- Squeegee solution away from edges and corners.




NOTE: Flip and change pads as needed.



STEP 8

- Pick up solution using a wet vacuum.
- Absorb scrubbing solution from corners, baseboards & squeegee trails with rinse mop


NOTE: Steps #7 and #8 can be done as one step with an autoscrubber, if available.



STEP 9

- Move to next 10 ft. by 20 ft. area and repeat Step 4 through Step 9.

NOTE: Change mop bucket solution when it becomes dirty and after every use.




STEP 10

- Using a clean rayon mop, submerge mop in clear water mop bucket.
- Apply water liberally to surface.
- Pick up solution with wet vacuum.
- Empty and rinse mop bucket.



NOTE: Step #10 be done as one step with an autoscrubber, if available.



STEP 11

- Recoat floor adding 2 - 3 finish layer(s) following the correct Finish Application Procedure for your floor.